

Installing the Segal Konica Minolta Bizhub C258 Printer – Instructions for Windows

First, download the Windows printer driver from the Konica Minolta drivers download page:

<https://onyxweb.mykonicaminolta.com/onestopproductsupport?appMode=public&productId=1876>

Click on the **Drivers** tab, then select the Windows version corresponding to the version installed on your computer (most likely Windows 10), then the **PCL** tab, to download the driver file (named **C759 C658_C368_C287_C3851_Series_PS_PCL_FAX_v11.1.x.0.zip**). After you've downloaded the file, navigate to the location where you downloaded it, double-click the file to extract the files to your computer and take note of where you extract the files – you will need to know this in the next section, to add the printer.

Add the printer:

- From the **Start** menu, Search for and select **Control Panel**
- Click on **Devices and Printers**.
- In the taskbar, click **Add a printer**
- Click **Add a network, wireless or Bluetooth printer**
- Click **The printer that I want isn't listed**
- Select **Add a printer using a TCP/IP address or hostname**, and click **Next**
- For Device Type, select **TCP/IP Device**, for Hostname or IP address, type: **129.105.102.61** and UN-check "Query the printer and automatically select the driver to use". Click **Next**
- Click the **Have Disk...** button.
- Click **Browse...** and navigate to where you extracted the printer driver files.
- Double-click folders in succession (downloaded folder location → Driver → Drivers → PCL → EN → Win_x64) until you see **KOAXPJ__.INF** and double-click this file – then click **OK**
- Select the **KONICA MINOLTA C658SeriesPCL 6** and click **Next**
- *Recommended:* Modify the name to identify this printer, e.g.: **Segal first floor KONICA MINOLTA C258 PCL** (or whatever best identifies this printer for you)
- Click **Next**
- Select the **Do not share this printer** radio button and click **Next**
- **UNCHECK Set as the default printer** if it is checked (unless this will be your default printer).
- **DO NOT** print a test page; you need to configure this printer first (see next section, to configure the printer).
- Click **Finish**.

Configure the printer:

- From the **Start** menu, Search for and select **Control Panel**
- Click on **Devices and Printers**
- Right-click on **Segal first floor KONICA MINOLTA C258** (or whatever you named it) and select **Printing preferences**
- Click on the **Other** tab
- **UNCHECK** both **Excel Job Control** and **Remove White Background**
- Click **Apply**, then click **OK**
- Close the Devices and Printers windows

You should now be able to print to this printer.